



Tech Info Library

Pascal: Speeding up Pascal text file reading (2 of 3)

```
BEGIN
  IF BUFINDEX >= NOTNULLS THEN FILLBUFFER;
      (* If the buffer needs refilling,
      go and get another buffer. *)
  IF NOT EMPTY THEN BEGIN
      (* If the file is not yet empty,
      then do the following: *)
      LINELEN := SCAN (BUFSIZE, = CHR(13), BUFFER [BUFINDEX]);
      (* Set LINELEN to the number of
      characters from the current
      buffer pointer position
      (BUFINDEX) to the next carriage
      return in the buffer.*)
      IF BUFFER [BUFINDEX] = CHR (16) THEN BEGIN
          (* If the character at the buffer
          index is an ASCII DLE, then we
          have to unpack the leading
          spaces. *)
          INDENT := ORD (BUFFER [BUFINDEX + 1]) - 32;
          (* Set INDENT to the number found
          at BUFINDEX + 1, the number
          of space characters to
          insert. *)

          (*$R-*)
          LINE [0] := CHR (LINELEN + INDENT - 2);
          (*$R+*)
          (* Turn off Range Checking so we can
          manually change the string length. Set
          the length of LINE to the number we had
          already gotten plus the number of spaces
          to unpack, throwing away two bytes for
          the DLE and count bytes. Turn Range
          Checking back on.*)
          IF INDENT > 0 THEN FILLCHAR (LINE [1], INDENT, ' ');
          (* If there are spaces, then fill in the
          appropriate number of them, starting
          with the first position in the new
          string. *)
          IF LINELEN > 2 THEN MOVELEFT (BUFFER [BUFINDEX + 2],
          LINE [1 + INDENT], LINELEN - 2);
          (* If the string is more than 2
          characters long, then move the rest of
          it from the buffer into the string
          starting just after the leading spaces
```

```

                                previously inserted. *)
END ELSE BEGIN
                                (* No DLE character was found. That
                                means straight ASCII. *)
                                (*$R-*)
LINE [0] := CHR (LINELEN);
                                (*$R+*)
                                (* Turn Range Checking off, set the
                                length of the string to LINELEN, and
                                turn Range Checking back on. *)
IF LINELEN > 0 THEN MOVELEFT (BUFFER [BUFINDEX],
                                LINE [1], LINELEN);
                                (* Move the characters from the buffer
                                into LINE as above. *)
                                END;
BUFINDEX := BUFINDEX + LINELEN + 1;
                                (* Sets the pointer to the first
                                character of the next string in the
                                buffer for the next time through. *)
                                END;
END;

```

Here's a program that demonstrates the difference in speed between the two methods of reading strings:

```

PROGRAM QUICKREAD; (* Very fast line read routine *)
CONST BUFSIZE = 1024;
      BUFLLEN = 1023;
      FILENAME = 'QWERTY9.TEXT';
(* Probably not on user disk *)
VAR LINE: STRING;
    INFILE: FILE;
    TEXTFILE: TEXT;
    CH, OPTION: CHAR;
    EMPTY, HELL_FREEZES_OVER: BOOLEAN;
    ERROR: INTEGER;
    NOTNULLS: 0..BUFSIZE;
(* # of non-null chars *)
    BUFINDEX: 0..BUFSIZE;
(* Index within buffer *)
    BUFFER: PACKED ARRAY [0..BUFLLEN] of CHAR;

```

Apple Tech Notes

Keywords: <None>

=====

This information is from the Apple Technical Information Library.

19960215 11:05:19.00

Tech Info Library Article Number: 652